

FUSED 5 DRAWER MINI TOTE

5 drawer unit is 11 1/8" HI, 7 1/4" W, 8" D

- 1 LARGE TABLE RUNNER
 - 1 ROLL HEAT AND BOND REGULAR (PARTIAL ROLL)
 - 1 1/4 YARD LINING/TRIM MATERIAL
 - 2 12" NYLON ZIPPERS
- THREAD TO MATCH PROJECT TRIM/LINING

DIRECTIONS:

FUSE APPROXIMATELY 70" WIDE X WIDTH OF RUNNER ON WRONG SIDE WITH HEAT AND BOND AS DIRECTED ON PACKAGE. WHEN COOLED, PULL OFF PAPER AND APPLY LINING MATERIAL TO FUSED SIDE OF RUNNER AND FUSE WELL. (IF YOUR RUNNER IS LINED, CUT OUT THE LINING.)

CUT OUT PIECES: (SEE DIAGRAM)

- 1 F (FRONT) 7 1/2" W X 11 1/4" (FUSSY CUT FOR DESIGN) (#1 DIAGRAM)
- 1 L (LEFT SIDE) 11 3/4" W X 13 1/4" H (FUSSY CUT FOR DESIGN) (#2)
- 1 R (RIGHT SIDE) 11 3/4" W X 13 1/4" H (FUSSY CUT FOR DESIGN) (#3)
- 1 T (TOP & FLAP) 9 1/4" W X 12 1/2" L (FUSSY CUT FOR DESIGN) (#4)
- 1 B (BASE) 9 3/4" W X 10 1/4" L (#5)
- 1 2 1/4 – 3" WIDE X 8" HANDLE (#5)

LINING:

- 1 CUT BINDING 2 1/4" W X 31" LONG FOR FRONT PANEL
- 1 4" X 13" FUSED LINING (RE-CUT INTO 1" STRIPS)
- 1 1" X 21" FUSED LINING TO BIND HANDLE

- 1 4" X WIDTH OF LINING FOR BINDING BASE OF TOTE
- 1 3 1/2" X WIDTH OF LINING FOR BINDING TOP OF TOTE

- #1,2,3 MARK 1" ACROSS BOTTOM AND 3/4" ACROSS TOP FOR SEWING LINES.
- #2 MARK 8" FROM LEFT BOTTOM EDGE TO SEWING LINE (CLIP)
AND 3/4" FROM LEFT TOP EDGE TO SEWING LINE (CLIP)
- #3 MARK 1" FROM RIGHT BOTTOM EDGE TO SEWING LINE (CLIP)
AND 3/4" FROM RIGHT TOP EDGE TO SEWING LINE (CLIP)
- #4 MARK 1" FROM BOTTOM AND 3/4" FROM TOP FOR SEWING LINES
- #5 BASE AND HANDLE NEED NO MARKINGS

SASHING, BINDING ETC.

FRONT PANEL (#1): (2 1/4" X 31" BINDING STRIP), FOLD DOWN CENTER AND SEW ONTO BACK SIDE WITH 3/8" SEAM. TURN TO FRONT AND STITCH IN PLACE. BIND ALL BUT BOTTOM OF PANEL. (AROUND 3 SIDES)

ZIPPERS WILL BE SEWN TO FRONT PANEL ON BOTH SIDES OF PANEL

FUSED LINING STRIPS: BINDING BODY OF TOTE (FRONT ZIP EDGES)

R, L BODY PANELS (#2,3): FUSE FRONT EDGES; FOLD TWO OF THE LINING STRIPS DOWN THE MIDDLE AND ENCASE THE FRONT EDGES (ZIPPER AREA) THEN PULL OFF PAPER. LAY THE PANELS (L, F, R) TOGETHER LINING UP THE BOTTOM EDGES. INSERT ZIPPERS FROM TOP OF FRONT PANEL (ZIPPER CLOSED) . ZIPPER WILL OVERHANG BOTTOM EDGE. AT THE 1" MARKS ON PANELS TACK THE ZIPPER TEETH SO THE ZIPPER STOPS AT THIS POINT. CUT OFF EXCESS ZIPPER AT BOTTOM AND OPEN TEETH TO THE TACK POINT.

CLOSE BODY AT BACK: USE TWO 1" X 13" BINDING STRIPS TO CLOSE THE TOTE AT THE BACK. MEET THE TWO PANELS AT CENTER BACK, PLACE ONE BINDING ON INSIDE AND ONE ON OUTSIDE (1/2" ON EACH SIDE OF BODY) TO CONNECT THEM (OPEN ZIPPERS FOR EASE OF FUSING & SEWING) FUSE IN PLACE. SEW WITH DECORATIVE STITCH DOWN BOTH EDGES OF BINDINGS.

TOP OF TOTE:

BIND THE HANDLE WITH THE REMAINING 1" X 13" BINDING STRIP MITER CORNERS AND TOP STITCH. PLACING THE HANDLE 4" FROM BACK EDGE TO TOP PANEL & 1 1/2" FROM SIDE EDGES, SEW THE HANDLE DOWN AT BOTH ENDS.

PIN THE BODY OF TOTE TO THE TOP OPENING, CENTERING, TO THE CLIPPED AREA (3/4" CORNERS OPEN AT EACH END). SEW ACROSS THE BACK CORNER TO CORNER. THEN SEW FROM THOSE CORNERS TO FRONT. BIND WITH 3 3/4" STRIP SEWING WITH 3/8" SEAM ALLOWANCE ON UNDERSIDE, FOLD OVER TOP AND STITCH DOWN MITERING CORNERS. FOLD THE FLAP DOWN OVER FRONT PANEL AND TOP STITCH WITH ABOUT A 1/4" PLEAT. THE FLAP WILL STAY IN PLACE (NO SNAP, BUTTON OR TIE NEEDED)

BASE OF TOTE:

PLACE BASE WITH RIGHT SIDE DOWN ON TABLE TOP. LINE UP THE BODY WITH THE OUTSIDE EDGES. (THE CORNERS WILL OPEN UP) SEW AT THE 1" MARK. BIND AS YOU DID THE TOP.

See page 4 for views at each stage of construction.

Original Pattern Designed by: Ethel Granger

